



Ciphr Activation Guide

Samsung AFW QR Code





*Images and steps may be different
depending on your device.




Step 1

Turn on the Samsung Device. On the "Let's go!" screen, tap anywhere on the screen 7 times (do not tap the arrow).

This will launch the device camera.

Scan the QR Code attachment provided by Ciphir or use this QR Code below:




Step 2

Once on the Wi-Fi selection screen, connect to a secure Wi-Fi network.


This step is mandatory.

Once connected, hit "**Next**".




Step 3

On the phone setup screen, tap on **"Accept & continue"**.



Step 4

In the Terms and Conditions screen, only select **"End User License Agreement"** and **"Privacy Policy"**, then hit **"Next"**.




Step 5

On the Device Activation screen, input the BES email, check **"I accept the license agreement"**, then hit **"Next"**.



Step 6


On the next screen, input the password **"start"** and tap on **"Activate my device"** to start the UEM setup.



Step 7


On the next screen, you will be prompted to create the device password. Please follow the requirements indicated on the screen for the password.

(8 characters, 1 upper case letter, 1 lower case letter, 1 number and 1 symbol).




Step 8

Select to **"Hide content"** for the lock screen notifications.




Step 9

The UEM client should now show **"Compliant"** and the apps should start to download. They will install automatically on the device. Slide down the notification tray to view the download progress of each app.




Step 10

Once all 3 Ciphr apps have downloaded, tap on **"Ciphr Mail"**.




Step 11

Input the "**Ciphre Activation Code**" and this will start the set-up of the Ciphre suite. Simply follow the on screen instructions to create your password and finalize your account setup.




Step 12

Go in Android's settings, choose **Connections**. Turn the Wifi OFF. Then tap on **Mobile Networks**.



Step 13


Make sure that **Data Roaming** is **ON** then tap on **Access Point Names** and tap on **ADD**.



Step 14


Enter **"data"** in the **Name** field then enter the APN that you were instructed to use in the **APN** field. All the other field remain **Not set**. Tap on the three dots and choose **SAVE**.

Back in the Access Point Names list, make sure the APN you just created is selected (blue dot).



Step 15

In Android settings tap on **Apps**. Tap on the three dots and choose **Special Access** then tap on **Optimize Battery Usage**.



Step 16

Tap on the filter drop down and choose **All apps**. Then make sure that the following apps are **NOT** set as Optimized:
Blackberry Connectivity
Ciphir Mail
Ciphir Text



Step 17

In Android settings tap on **Security** then on **Secure Startup**. Make sure that **Require password when device turns on** is selected then choose **OK** and confirm by entering the device's password.

Note: Secure Startup is enabled by default on some devices and the option might not show in the settings menu for those.

Having trouble with your activation? Please contact your Ciphr reseller for additional support.

